GCUSB-nStep cserial commands @ 2010-2013 GC For use in development of any RTS2 driver

Position manipulation

Device supports saving 5 stored positions for later GoTo

GoTo saved position 'index' 0 to 4: :GX# X = 0 to 4

sprintf(buf,"#:G%01d#", index);

No response returned

Save current position : CQX# at index 'X' = 0 to 4:

sprintf(buf,"#:CQ%01d#",index);

No response returned

Maintained in device flash acroos power cycles

Read saved position :RQX# at index X =0 to 4:

sprintf(buf,"#:RQ%01d#",index);

Response:

num_bytes = read(portFID,buf1,7);

Format +123456 or -123456

Force set current position, NOT a Move command, SIGN and 6 digits required, e.g. +123456 or -123456

Example for '0'

sprintf(buf,"#:CP+000000#");

No response returned

Device current position maintained in device flash acroos power cycles

Read current position:

sprintf(buf,"#:RP");

Last position maintained in device flash acroos power cycles \bar{a}

Response:

num_bytes = read(portFID, Pos, 7);
7 bytes with sign, e.g. -123456 or +123456 or +000000

Set max step speed, range 1 to 254, lower is faster

Step speed roughly in ms is value/1465

Example value = 1, rate = 1465 steps/second

value = 2, rate = 1465/2 = 732 steps/second

value = 3, rate = 1465/3 = 488 steps/second

value = 10, rate = 1465/10 = 146 steps/second

sprintf(buf,":CS%03d#", MaxSpeed);

No response returned

Maintained in device flash acroos power cycles

Set requested current step rate

Same range and values as max step rate above
sprintf(buf,":CO%03d#", Step Size);

```
If step speed is faster than max step speed, command ignored No response returned
```

Maintained in device flash acroos power cycles

Set stepping phase:

```
sprintf(buf,":CW%01d#", Phase);
Range 0 to 2
Device supports 3 different step sequences which handle all
wiring orders
going to motor
See http://www.stepperworld.com/Tutorials/pgUnipolarTutorial.htm
Search for: "Shortcut for finding the proper wiring sequence"
Maintained in device flash acroos power cycles
```

Read current temperature

```
sprintf(buf,"#:RT");
Response:
    num_bytes = read(portFID,Temp,4);
Four bytes including sign, fixed point
Example: -101 = -10.1C, +275 = +27.5C
If response = -888 then no temperature sensor found
```

Move focuser forward, backward using wave/half/full torque stepping

```
case DIR FORWARD:
            sprintf(buf,":F0%d%03d#",mode,count);
            break;
      case DIR REVERSE:
            sprintf(buf,":F1%d%03d#",mode,count);
      case DIR STOP:
            sprintf(buf,":F1%d%03d#", mode, 0);
            break;
No Response returned
Valid range 001 to 999 steps for 'count'
'Mode' is stepping type:
      0 - wave (1 wire energized per step
      1 - half alternate 1 wire, 2 wire energized/step
      2 - fü11 torque (2 phases active per step)
Can be written at any time, even during current stepping
To force a stop, send 000 in last direction commanded
```

Focuser moving?

```
sprintf(buf1,"S");
Response: 1 byte, '0' not moving, '1' moving
```

Set coil state after move:

```
sprintf(tempstr,":CC1"); <-- de-energize coil
    sprintf(tempstr,":CC0"); <-- Keep coils energized, WATCH for
motor heating!!!
    No response returned</pre>
```

Maintained in device flash acroos power cycles

Example sequence

```
Check if device is usb-nStep
```

```
Send 0x6 binary, Response 1 byte 'S' if usb-nStep
            , read saved current position 7 chars leading '+' or '-'
      :RC
            , read coil on/off after stepping, 1 byte response 0, 1 or
2
            , read step rate, 3 byte response 001 to 254
      :RO
            , read max step rate, 3 byte response 001 to 254
      :RS
          , Read phase wiring selection, 1 byte response 0, 1 or 2
      :RT , Read temp to determine if sensor attached, 4 byte
response SXXX fixed point temperature, -888 no sensor connected
Items stored in device flash:
            Read max speed (:RS)
                                         buf[0]=':';
buf[1]='R';buf[2]='S';buf[3]=0;
                                         num bytes =
write(portFID, buf, 3);
                                         num bytes =
read(portFID, buf1, 3);
                                         buf1[3] = 0;
                                         MaxSpeed = atoi(buf1);
            Read current step rate (:RO)
                                         buf[2] = 'O';
                                         num bytes =
write(portFID, buf, 3);
                                         num bytes =
read(portFID, buf1, 3);
                                         buf1[3] = 0;
                                         CurrentStepRate = atoi(buf1);
            Read motor wiring phase selection (:RW)
                                         buf[2] = 'W';
                                         num bytes =
write(portFID, buf, 3);
                                         num bytes =
read(portFID, buf1, 3);
                                         buf1[1] = 0;
                                         RigelPhase = atoi(buf1);
            Read stored positions (:RQX X = 0 to 4)
                                         buf[0]=':';
buf[1]='R';buf[2]='Q';
                                         for(i=0;i<5;i++)
                                             buf[3] = (char)(i +
0x30); buf [4]=0;
                                             num bytes =
write(portFID, buf, 4);
                                             num bytes =
```

```
read(portFID, buf1, 7);
                                            buf1[7] = 0;
                                            Rigel Positions[i]=
atoi(buf1);
                                        }
                Action and/or Response
      ctrl-F
                 response 'n' for gcusb-nFOCUS focuser, 'S' for gcusb-
nStep
                 response 1 if moving focuser, 0 if not
      0000
                 Force reboot in flash upgrade mode (HID device)
      :FDSXXX# Focus in dir D at step type S for XXX steps (S = 0 =
F, 1=H, 2=T)
                 Sending XXX = 000 = stop all motion
     :COXXX# Configure step time, increment = 0.68ms
:CFXXX# Configure focus off time (NOT used gcusb-nstep)
      :CSXXX#
                 Configure Max Speed for main module, 1 = fastest, 250
= slowest
                Keep coils X = on(=0)/off(=1) after stepping
      :CCX
      :CWX
                 Set phase array 0, 1 or 2, three selections cover all
wiring possible
      :CPSXXXXXX Force set current position to signed value with 6
diaits
                Read focus ON time (current step rate)
      :RO
     ·RF
             Read focus off time - NOT USED gcusb-nStep
              Set max speed allowed to step from the speed dial
      :RS
                Read temp, format SXXX fixed point, e.g. +123 =
+12.3C, -054 = -5.4C, -888 for no sensor attached
      :RC
                Read coil on/off after stepping, 0 = keep on, 1 =
turn off after step
                Read current position, returns signed number "+/-
XXXXXX" sign + 6 digits returned
      :RQX Read saved position X, X = 0 to 5
      :CQX Save position X with the value of the current position
                  Goto saved position X
      :GX
```

Debug commands, drive phase wiring directly from computer side

:PSX# Output X to port B lower 4 bits

Change low level stepping sequences, NOT maintained across reboots

:SXXXXX...# Input lower 4 bits of 72 bytes to stepper array

Can be used by gcusb-nStep modular controller w/display or gcusb-nStep with wireless adapter for smart phone wireless link to debug display

```
:RDXYAAA Write/Read from display
    X = Count out to display
    Y = count in from display
    AAA.. = out display then read Y back
:CDXAAA Write to display
    X = count, AAA = data out, NO terminating #!!!
```

Advanced commands for using internal temperature compensation

_		Configure temp change for comp, Sign + XXX , fixed
point	decimla -09	
	:TSXXX#	Configure temp comp move, steps per temp
change=XXX		
	:TAX	Configure temp comp 0=off, 1=one shot, 2=auto
	:TBXXX#	Configure temp comp backlash, steps=XXX
	:TI	Prime for manual comp
	:TCXX#	Configure temp comp timer, range 1 to 75
seconds		
	:RA	Read temp change for comp, format SXXX fixed point
	:RB	Read temp step for comp, format XXX
	:RG	Read temp comp state, format X
	:RE	Read temp comp backlash, format XXX
	:RH	Read temp comp timer